

VCE4Plus



Everything you need to prepare, learn & pass your certification exam easily.

Pass Your Next Certification Exam Fast!

365 days free updates. First attempt guaranteed success.

Choose the version that fits your needs	PDF Version	Desktop Test Engine	Online Test Engine
Latest and Up-to-Date exam dumps with real exam questions answers.	✓	✓	✓
Get 12-Months free updates without any extra charges.	✓	✓	✓
Experience same exam environment before appearing in the certification exam.	✗	✓	✓
100% exam passing guarantee in the first attempt.	✓	✓	✓
20% discount on more than one license and 30% discount on 5+ license purchases.	✗	✓	✓
100% secure purchase on SSL.	✓	✓	✓
Completely private purchase without sharing your personal info with anyone.	✓	✓	✓

<http://www.vce4plus.com>

Accurate exam material ensure you pass for sure by your first attempt - VCE4Plus

Exam : **300-085**

Title : Implementing Cisco
Collaboration Application v1.0

Vendor : Cisco

Version : DEMO

NO.1 Which two statements about configuring Cisco VCS for provisioning are true? (Choose two)

- A. Cisco VCS TMSPE supports provisioning.
- B. Cisco VCS Control supports provisioning
- C. Cisco Conductor is needed to support provisioning.
- D. Cisco VCS user accounts replicate between all Cisco VCS configured in Cisco TMS.
- E. Cisco VCS Express supports provisioning.

Answer: A,B

NO.2 The Cisco TMS administrator wants to test outbound calls that originate from a video device that is added to the Cisco TMS. Which path does the administrator use to complete this operation in the Cisco TMS interface?

- A. Booking > New Conference > Dial External tab
- B. Systems > Provisioning > Users > Call Status
- C. Phone Books > Dial External tab
- D. Systems > Navigator > Endpoint > Call Status tab in the endpoint configuration

Answer: D

NO.3 In Cisco Unity Connection, which two methods can you use to segregate the global dial and message addressing space? (Choose two.)

- A. SIP trunk
- B. partitions
- C. route patterns
- D. translation patterns
- E. search spaces
- F. hunt pilot

Answer: B,E

NO.4 Cisco Unified Communications Manager IM & Presence supports which two protocols? (Choose two.)

- A. MVA
- B. CT1/QBE
- C. H.323
- D. XMPP
- E. MGCP

Answer: B,D

NO.5 What are two valid privilege levels for subscribers on Cisco Unity Express? (Choose two.)

- A. root
- B. broadcast
- C. super user
- D. admin
- E. guest

Answer: B,C

NO.6 Which two parameters are required when you configure the Voice Profile for Internet Mail location on Cisco Unity Express? (Choose two.)

- A. destination type
- B. display name
- C. dial ID
- D. location ID
- E. Simple Mail Transfer Protocol domain name
- F. domain name or IP address

Answer: D,F

NO.7 Which Cisco TMS extension integrates Cisco TMS with IBM Lotus Domino Server 7.0.x, 8.0.x, 8.5.x?

- A. TMSXE
- B. TMSXN
- C. TMSPE
- D. TMSBA

Answer: B

NO.8 Which call launch in TMS reserves the room and generates the call route?

- A. No Connect
- B. One Button to Push
- C. Automatic Connect
- D. Reservation

Answer: A

NO.9 An engineer is configuring Binary Floor Control Protocol for a CTS 3100. What are three required configuration items? (Choose three.)

- A. configure the SIP Trunk
- B. configure the VCS Zone
- C. configure the CUCM service parameters
- D. configure the Device Profile
- E. configure the SIP Profile
- F. configure the VCS Domain

Answer: A,B,E

NO.10 Where can an engineer change a user provisioning password?

- A. Cisco TMSPE User Provisioning page
- B. Cisco TMSPE account AD credentials
- C. Cisco TMPSE account settings
- D. Cisco TMSPE User import page

Answer: A

NO.11 Which two appear under the System Settings section of Cisco Unity Connection? (Choose two.)

- A. service parameters
- B. bulk administration tool
- C. interview handlers
- D. telephony integration
- E. licenses

Answer: A,E

NO.12 Refer to the exhibit.

```
!  
interface Integrated-Service-Engine1/0  
  ip unnumbered Loopback0  
  service-module ip address 10.1.131.2  
255.255.255.0  
  service-module ip default-gateway 10.1.131.1  
  no keepalive  
!
```

Which six of the following commands are required to configure a dial peer that will allow voice-mail messages to be left on Cisco Unity Express for Unified Communications Manager Express users? The Cisco Unity Express module uses a pilot number of 4100. (Choose six.)

- A. codec g711ulaw
- B. dtmf-relay h245-alphanumeric
- C. destination-pattern 4100
- D. session target ipv4:10.1.131.2
- E. session target ipv4:10.1.131.1
- F. dial-peer voice 4100 pots
- G. dial-peer voice 4100 voip
- H. codec transparent
- I. dtmf-relay sip-notify
- J. no vad

Answer: A,C,D,G,I,J

NO.13 In Cisco Unity Express, where are privilege levels assigned?

- A. Administrators
- B. User Groups
- C. Mailbox Admins
- D. Users

Answer: B

NO.14 Which three client applications use the features of the Cisco Unified IM and Presence server? (Choose three.)

- A. Cisco Unified Personal Communicator
- B. Cisco Jabber Voice for Android or iPhone
- C. Cisco Jabber Video for TelePresence
- D. Cisco IP SoftPhone
- E. Cisco IP Communicator
- F. Skype
- G. Cisco UC Integration for Microsoft Lync (CUCI-Lync)
- H. Cisco Jabber for Windows or Mac

Answer: A,G,H

NO.15 You are integrating Cisco Unity Connection with Cisco Unified Communications Manager to provide voicemail services for an organization. Which protocol does Cisco Unity Connection use to access the Cisco Unified Communications Manager database?

- A. VXML
- B. JTAPI
- C. SOAP
- D. AXL

Answer: D

NO.16 On Cisco TelePresence Management Suite, which two call control devices are supported for call control and setup? (Choose two.)

- A. Cisco Unified Communications Manager
- B. Cisco Unified Border Element
- C. Cisco TelePresence Video Communication Server
- D. Cisco Unified Communications Manager Express
- E. any SIP-capable call control system

Answer: A,C

NO.17 What does the Primary Extension column define when importing users?

- A. the main extension that callers dial to reach a user
- B. the mailbox ID that is assigned by Cisco Unity Express during import
- C. the pilot number that is used by Cisco Unified Communications Manager Express to access Cisco Unity Express
- D. the primary extension that is to be used for CFNA and CFB

Answer: A

NO.18 A Cisco Unity Connection System has users imported from the Cisco Unified Communications Manager, which in turn is integrated with LDAP. A user has reset the LDAP password and can authenticate with the organization's other systems, but cannot authenticate with Cisco Unity Connection Web application despite using the same and correct username and password. Which cause of this issue is true?

- A.** The Cisco Unity Connection administrator forgot to use the Synchronizing Users page, which must be performed when Cisco Unified CM is directly integrated to LDAP and Cisco Unity Connection imported the users from Cisco Unified Communications Manager.
- B.** The user is locked out of Cisco Unity Connection due to too many incorrect tries.
- C.** The user does not have the default web application authentication role associated in Cisco Unity Connection.
- D.** The Cisco Unity Connection administrator changed the PIN in Cisco Unity Connection admin for the user.
- E.** The Cisco Unity Connection administrator did not use the Synchronizing Users option.

Answer: A